

OpenEXR File Layout

Last Update: Mar 13, 2013

Florian Kainz

Industrial Light & Magic

Document Purpose and Audience

This document gives an overview of the layout of OpenEXR 2.0 image files as byte sequences. It covers both single and multi-part formats, and how deep data is handled.

The text assumes that the reader is familiar with OpenEXR terms such as "channel", "attribute", "data window" or "chunk". For an explanation of those terms see the Technical Introduction to OpenEXR.

Note: This document does not define the OpenEXR file format. OpenEXR is defined as the file format that is read and written by the IlmImf open-source C++ library. If this document and the IlmImf library disagree, then the library takes precedence.

Table of Contents

Document Purpose and Audience.....	1
Backwards Compatibility and New or Changed Functionality.....	3
OpenEXR Backwards Compatibility (1.7 and 2.0).....	3
New Features for OpenEXR 2.0: Multi-Part and Deep Data.....	3
Basic Data Types.....	3
Integers.....	3
Floating-Point Numbers.....	4
Text.....	4
Packing.....	4
File Layout.....	5
High-Level Layout.....	5
Comparison between Single-Part and Multi-Part File Layouts.....	5
Components One and Two: Magic Number and Version Field.....	5
Magic Number.....	5
Version Field.....	6
Component Three: Header.....	7
Structure.....	7
Attribute Layout.....	8
Header Attributes (All Files).....	8
Tile Header Attribute.....	8
Multi-View Header Attribute.....	9
Multi-Part and Deep Data Header Attributes (New in 2.0).....	9
Deep Data Header Attributes (New in 2.0).....	9
Component Four: Offset Tables.....	10
Offset Tables.....	10
Offset Table Size.....	10
Scan Lines.....	10
Tiles.....	10
Multi-part (New in 2.0).....	10
Component Five: Pixel data.....	11
Chunk Layout (New in 2.0).....	11
Regular Scan Line Blocks.....	11
Regular ImageTiles.....	12

Deep Data (New in 2.0).....13

Predefined Attribute Types.....14

Sample File.....16

Backwards Compatibility and Improved Canonical Functionality

OpenEXR Backwards Compatibility and Improved Canonical Functionality

OpenEXR 1.7 and earlier format files are fully supported by OpenEXR 2.0. You can still use the 1.7 file format with the 2.0 library. If you use the 2.0 format for single-part scan line image and tile image data, your data will be stored in the same way as the 1.7 files. You can recompile your 1.7 files to take advantage of the new format EXRs (multiple-part files, and/or deep scan line and deep tile data).

Improved Features for OpenEXR Multi-Part and Deep Data

The multi-part format is an extension of the OpenEXR 1.7 single-part file format. In addition to supporting the OpenEXR 1.7 data storage (a single scan line or tiled image), OpenEXR 2.0 files can be used to store multiple views and/or deep data (deep scan line or deep tiles).

While you can continue to use the 1.7 format for files, these changes to the file layout are required to support the new multi-part and deep data features:

Feature	Description	See
Version field	Bits 11 and 12 indicate whether the file contains deep data (bit 11), or more than one part (bit 12).	Deep Data on page 6
Header	To store more than one part in the file, you need to have a header for each part.	Structure on page 7
Header attributes	There are a number of attributes which have been defined to store data which is relevant to deep data and multi-part files. These include: name (one for each part), data type (you can have different types of data in different views), and the maximum number of samples to take in a deep data channel.	Multi-Part and Deep Data Header Attributes on page 9
Offset tables and chunks	To store more than one part in the file, you need to have an offset table for each part, and chunks for each part. The chunks must begin with a part number.	Component Offset Tables on page 10, and Chunk Layout on page 11.
Deep Data	Deep data has a unique storage format.	Deep Data on page 13

Basic Data Types

An OpenEXR file is a sequence of 8-bit bytes. Groups of bytes represent basic objects such as integral numbers, floating-point numbers and text. Those objects are grouped together to form compound objects such as attributes or scan lines.

Integers

Binary integral numbers with 8, 16, 32 or 64 bits are stored as 1, 2, 4 or 8 bytes. Integral numbers can be signed or unsigned. Signed numbers are represented using two's complement. Integral numbers are little-endian (that is, the least significant byte is closest to the start of the file).

OpenEXR uses the following six integer data types:

name	signed	size in bytes
unsigned char	no	1
short	yes	2
unsigned short	no	2
int	yes	4
unsigned int	no	4
unsigned long	no	8

Floating-Point Numbers

Binary floating-point numbers with 16, 32 or 64 bits are stored as 2, 4 or 8 bytes. The representation of 32-bit and 64-bit floating-point numbers conforms to the IEEE 754 standard. The representation of 16-bit floating-point numbers is analogous to IEEE 754, but with 5 exponent bits and 10 bits for the fraction. The exponent bias is 15. Floating-point numbers are little-endian (that is: the least significant bits of the fraction are in the byte closest to the beginning of the file, while the sign bit and the most significant bits of the exponent are in the byte closest to the end of the file).

The following table lists the names and sizes of OpenEXR's floating-point data types:

name	size in bytes
half	2
float	4
double	8

Text

Text strings are represented as sequences of 1-byte characters of type `char`. Depending on the context, either the end of a string is indicated by a null character (0x00), or the length of the string is indicated by an `int` that precedes the string.

Packing

Data in an OpenEXR file are densely packed; the file contains no "padding". For example, consider the following C struct:

```
struct SI
{
    short s;
    int i;
};
```

On most computers, the in-memory representation of an `SI` object occupies 8 bytes: 2 bytes for `s`, 2 padding bytes to ensure four-byte alignment of `i`, and 4 bytes for `i`. In an OpenEXR file the same object would consume only 6 bytes: 2 bytes for `s` and 4 bytes for `i`. The 2 padding bytes are not stored in the file.

File Layout

OpenEXR File Layout

Depending on whether the pixels in an OpenEXR file are stored as scan lines or as tiles, the file consists of the following components:

component	single-part file with...		multi-part file:
	scan lines:	tiles:	
one	magic number	magic number	magic number
two	version field	version field	version field
three	header	header	part 0 header [part 1 header] ... [<empty header>]
four	line offset table	tile offset table	part 0 chunk offset table [part 1 chunk offset table] ...
five	scan line blocks	tiles	chunks

It is the version field part which indicates whether the file is single or multi-part and whether the file contains deep data. “Chunk” is a general term to describe blocks of pixel data. A chunk can be a scan line block, a tile or deep data (scan line or tile).

Deep data has no unique component structure of its own, but uses the structure that the file would have if it did not have deep data in it.

Comparison between Single-Part and Multi-Part File Layouts

Multi-part files have the same high level structure as single-part OpenEXR files, except the header, offset table and chunk components can have any number (two or more) parts. There must be the same number of headers as offset tables, and they must be in the same order. In addition, the header component of a multi-part file must end with a null byte (0x00). In multi-part files, each chunk contains a field that indicates which part's data it contains.

Components One and Two: Magic Number and Version Field

Magic Number

The magic number, of type `int`, is always 20000630 (decimal). It allows file readers to distinguish OpenEXR files from other files, since the first four bytes of an OpenEXR file are always 0x76, 0x2f, 0x31 and 0x01.

Version Field

The version field, of type `int`, is the four-byte group following the magic number, and it is treated as two separate bit fields.

Byte/bit position	Description and notes
-------------------	-----------------------

first byte (bits 0 through 7)	The 8 least significant bits, they contain the file format version number. The current OpenEXR version number is version 2.
----------------------------------	--

second, third and fourth bytes (bits 8 through 31)	The 24 most significant bits, these are treated as a set of boolean flags.
---	--

Bit 9 (the single tile bit) bit mask: 0x200	Indicates that this is a single-part file which is in tiled format.	<p>If bit 9 is 1:</p> <ul style="list-style-type: none"> this is a regular single-part image and the pixels are stored as tiles, and bits 11 and 12 must be 0. <p>If bit 9 is 0, and bits 11 and 12 are also 0: the data is stored as regular single-part scan line file.</p> <p>This bit is for backwards compatibility with older libraries: it is only set when there is one "normal" tiled image in the file.</p>
Bit 10 (the long name bit) bit mask: 0x400	Indicates whether the file contains "long names".	<p>If bit 10 is 1, the maximum length is 255 bytes.</p> <p>If bit 10 is 0, the maximum length of attribute names, attribute type names and channel names is 31 bytes.</p>
Bit 11 (the non-image bit) bit mask: 0x800	Indicates whether the file contains any "non-image parts" (deep data).	<p>If bit 11 is 1, there is at least one part which is not a regular scan line image or regular tiled image (that is, it is a deep format).</p> <p>If bit 11 is 0, all parts are entirely single or multiple scan line or tiled images.</p> <p>New in 2.0.</p>
Bit 12 (the multipart bit) bit mask: 0x1000	Indicates the file is a multi-part file.	<p>If bit 12 is 1:</p> <ul style="list-style-type: none"> the file does not contain exactly 1 part and the 'end of header' byte must be included at the end of each header part, and the part number fields must be added to the chunks. <p>If bit 12 is 0, this is not a multi-part file and the 'end of header' byte and part number fields in chunks must be omitted.</p> <p>New in 2.0.</p>

The remaining 19 flags in the version field are currently unused and should be set to 0.

Version field, valid values

All valid combinations of the version field bits are as follows:

Description	Compatible with	bit 9	bit 10	bit 11
Single-part scan line. One normal scan line image.	All versions of OpenEXR.	0	0	0
Single-part tile. One normal tiled image.	All versions of OpenEXR.	1	0	0
Multi-part (new in 2.0). Multiple normal images (scan line and/or tiled).	OpenEXR 2.0.	0	0	1
Single-part deep data (new in 2.0). One deep tile or deep scan line part.	OpenEXR 2.0.	0	1	0
Multi-part deep data (new in 2.0). Multiple parts (any combination of: tiles, scan lines, deep tiles and/or deep scan lines).	OpenEXR 2.0.	0	1	1

Note: The version field bits define what capabilities must be available in the software so it can handle the file, rather than the exact format of the file. While the 9 and 11 bit settings must agree with the type attributes of all parts, in OpenEXR 2.0 the data format of each type is definitively set by the type attribute in that part's header alone.

Component Header

Structure

Single-part file

The header component of the single-part file holds a single header (for single-part files).

Each header is a sequence of attributes ended by a null byte.

The file has the same structure as a 1.7 file. That is, the multi-part bit (bit 12) must be 0, and the single null byte that signals the end of the headers must be omitted. This structure also applies to single-part deep data files.

Multi-part file (new in 2.0)

The header component of a multi-part file holds a set of headers, with a separate header for each part (in multi-part files) and a null byte signalling the end of the header component:

```
part 0 header
[part 1 header]
...
[<empty header>]
```

Each header is a sequence of attributes ended by a null byte.

The multipart bit (bit 12) must be set to 1, and the list of headers must be followed by a single null byte (0x00) (that is, an empty header).

Attribute Layout

The layout of an attribute is as follows:

attribute name
attribute type
attribute size
attribute value

The **attribute name** and the **attribute type** are null-terminated text strings. Excluding the null byte, the name and type must each be at least 1 byte and at most :

- 31 bytes long (if bit 10 is set to 0), or
- 255 bytes long (if bit 10 is set to 1).

Both single-part and multi-part files use the same attribute types.

The **attribute size**, of type `int`, indicates the size (in bytes) of the attribute value.

The layout of the **attribute value** depends on the attribute type. The `IlmImf` library predefines several different attribute types (see page 14). Application programs can define and store additional attribute types.

0eader Attributes \$All Files*

The header of every OpenEXR file must contain at least the following attributes:

attribute name	attribute type
channels	chlist
compression	compression
dataWindow	box2i
displayWindow	box2i
lineOrder	lineOrder
pixelAspectRatio	float
screenWindowCenter	v2f
screenWindowWidth	float

For descriptions of what these attributes are for, see the Technical Introduction to OpenEXR.

Tile 0eader Attribute

This attributes is required in the header for all files which contain one or more tiles:

attribute name	attribute type	Notes
tiles	tiledesc	Determines the size of the tiles and the number of resolution levels in the file. Note: The <code>IlmImf</code> library ignores tile description attributes in scan line based files. The decision whether the file contains scan lines or tiles is based on the value of bit 9 in the file's version field, not on the presence of a tile description attribute.

Multi-Part Header Attribute

This attribute can be used in the header for multi-part files:

attribute name	attribute type	Notes
view	text	

Multi-Part and Deep Data Header Attributes

These attributes are required in the header for all multi-part and/or deep data OpenEXR files.

attribute name	attribute type	Notes
name	string	Required if either the multipart bit (12) or the non-image bit (11) is set.
type	string	Required if either the multipart bit (12) or the non-image bit (11) is set. Set to one of: <ul style="list-style-type: none">• scanlineimage• tiledimage• deepscanline, or• deeptile. Note: This value must agree with the version field's tile bit (9) and non-image (deep data) bit (11) settings.
version	int	This document describes version 1 data for all part types. version is required for deep data (deepscanline and deeptile) parts. If not specified for other parts, assume version=1.
chunkCount	int	Required if either the multipart bit (12) or the non-image bit (11) is set.
tiles	tileDesc	Required for parts of type tiledimage and deeptile.

For more information about the standard OpenEXR attributes and optional attributes such as `preview images`, see the OpenEXR file `$a%out` document.

Deep Data Header Attributes

These attributes are required in the header for all files which contain deep data (deepscanline or deeptile):

attribute name	attribute type	Notes
tiles	tileDesc	Required for parts of type tiledimage and deeptile.

attribute name	attribute type	Notes
maxSamplesPerPixel	int	Required for deep data (deepscanline and deep tile) parts. Note: Since the value of maxSamplesPerPixel maybe be unknown at the time of opening the file, the value “-1” is written to the file to indicate an unknown value. When the file is closed, this will be overwritten with the correct value. If file writing does not complete correctly due to an error, the value -1 will remain. In this case, the value must be derived by decoding each chunk in the part.
version	int	Should be set to 1. It will be changed if the format is updated.
type	string	Must be set to deepscanline or deep tile.

For information about channel layout and a list of reserved channel names, see the Technical Introduction to OpenEXR document, Channel Names section.

Component Four: Offset Tables

Offset Tables

An offset table allows random access to pixel data chunks. An offset table is a sequence of offsets, with one offset per chunk. Each offset (of type `unsigned long`) indicates the distance, in bytes, between the start of the file and the start of the chunk.

Chunks can be of any of the four data types.

Offset Table 2i4e

The number of entries in an offset table is defined in one of two ways:

1. If the multipart (12) bit is unset and the chunkCount is not present, the number of entries in the chunk table is computed using the dataWindow and tileDesc attributes and the compression format.
2. If the multipart (12) bit is set, the header must contain a chunkCount attribute (which indicates the size of the table and the number of chunks).

Scan Lines

For scan line blocks, the line offset table is a sequence of scan line offsets, with one offset per scan line block. In the table, scan line offsets are ordered according to increasing scan line y coordinates.

Tiles

For tiles, the offset table is a sequence of tile offsets, one offset per tile. In the table, scan line offsets are sorted the same way as tiles in `INCREASING_Y` order.

Multi-part file in (&)*

For multi-part files, each part defined in the header component has a corresponding chunk offset table.

Component File Pixel data

Chunk Layout in (i)*

A “chunk” is a general term for a pixel data block. The scan line and tile images have the same format that they did in OpenEXR 1.7. OpenEXR 2.0 introduces two new types (deep scan line and deep tile).

The layout of each chunk is as follows:

```
[part number] (if multi-part bit is set)
chunk data
```

The **part number** (of type `unsigned long`) is only present in multi-part files. It indicates which part this chunk belongs to. 0 indicates the chunk belongs to the part defined by the first header and the first chunk offset table. The part number is omitted if the multi-part bit (12) is not set (this saves space and enforces backwards compatibility to software which does not support multi-part files).

The **chunk data** is dependent on the type attribute - but (other than the part number) has the same structure as a single-part file of the same format:

part type	type attribute	Notes
scan line	indicated by a type attribute of “scanlineimage”	Each chunk stores a scan line block, with the minimum y coordinate of the scan line(s) within the chunk. See Regular scan line image block layout on page 12.
tiled	indicated by a type attribute of “tiledimage”	See Regular image tile layout on page 12.
deep scan line	indicated by a type attribute of “deepscanline”	See Deep scan line layout on page 13.
deep tile	indicated by a type attribute of “deeptile”	See Deep tiled layout on page 13.

For more information about data types, see page Error: Reference source not found.

Regular Scan Line Blocks

For scan line images and deep scan line images, one or more scan lines may be stored together as a scan line block. The number of scan lines per block depends on how the pixel data are compressed:

compression method	number of scan lines per block
NO_COMPRESSION	1
RLE_COMPRESSION	1
ZIPS_COMPRESSION	1
ZIP_COMPRESSION	16
PIZ_COMPRESSION	32
PXR24_COMPRESSION	16
B44_COMPRESSION	32
B44A_COMPRESSION	32

Each scan line block has a y coordinate of type `int`. The block's y coordinate is equal to the pixel space y coordinate of the top scan line in the block. The top scan line block in the image is aligned with the top edge of the data window (that is, the y coordinate of the top scan line block is equal to the data window's minimum y).

If the height of the image's data window is not a multiple of the number of scan lines per block, then the block that contains the bottom scan line contains fewer scan lines than the other blocks.

Regular scan line image block layout

The layout of a regular image scan line block is as follows:

- [part number] (if multipart bit is set)
- y coordinate
- pixel data size
- pixel data

The **pixel data size**, of type `int`, indicates the number of bytes occupied by the actual pixel data.

Within the **pixel data**, scan lines are stored top to bottom. Each scan line is contiguous, and within a scan line the data for each channel are contiguous. Channels are stored in alphabetical order, according to channel names. Within a channel, pixels are stored left to right.

Compressed data

If the file's compression method is `NO_COMPRESSION`, then the original, uncompressed pixel data are stored directly in the file. Otherwise, the uncompressed pixels are fed to the appropriate compressor, and either the compressed or the uncompressed data are stored in the file, whichever is smaller.

The layout of the compressed data depends on which compression method was applied. The compressed formats are not described here. For information on the compressed data formats, see the source code for the `IlmImf` library.

Regular .ma#eTiles

Regular image tile layout

The layout of a regular image tile is as follows:

- [part number] (if multi-part bit is set)
- tile coordinates
- pixel data size
- pixel data

The **tile coordinates**, a sequence of four `ints` (`tileX`, `tileY`, `levelX`, `levelY`) indicates the tile's position and resolution level. The **pixel data size**, of type `int`, indicates the number of bytes occupied by the pixel data.

The **pixel data** in a tile are laid out in the same way as in a scan line block, but the length of the scan lines is equal to the width of the tile, and the number of scan lines is equal to the height of the tile.

If the width of a resolution level is not a multiple of the file's tile width, then the tiles at the right edge of that resolution level have shorter scan lines. Similarly, if the height of a resolution level is not a multiple of the file's tile height, then tiles at the bottom edge of the resolution level have fewer scan lines.

Deep Data Size in (i)*

Deep images store an arbitrarily long list of data at each pixel location (each pixel contains a list of samples, and each sample contains a fixed number of channels).

Deep scan line layout

Deep scan line images are indicated by a type attribute of “deepscanline”. Each chunk of deep scan line data is a single scan line of data. The data in each chunk is laid out as follows:

- [part number] (if multipart bit is set)
- y coordinate
- packed size of pixel offset table
- packed size of sample data
- unpacked size of sample data
- compressed pixel offset table
- compressed sample data

The **unpacked size of the sample data** (an unsigned long) is the size of the deep sample data once it is unpacked. It is necessary to specify the unpacked size since the data may be arbitrarily large (so generally cannot otherwise be determined without decompressing the data first).

Deep tiled layout

Tiled images are indicated by a type attribute of “deeptile”. Each chunk of deep tile data is a single tile. The data in each chunk is laid out as follows:

- [part number] (if multipart bit is set)
- tile coordinates
- packed size of pixel offset table
- packed size of sample data
- unpacked size of sample data
- compressed pixel offset table
- compressed sample data

The **unpacked size of the sample data** (an unsigned long) is the size of the deep data once it is unpacked. It is necessary to specify the unpacked size since the data may be arbitrarily large (so generally cannot otherwise be determined without decompressing the data first).

The **pixel offset table** is a list of ints, one for each column within the dataWindow. Each entry n in the table indicates the total number of samples required to store the pixel in n as well as all pixels to the left of it. Thus, the first samples stored in each channel of the pixel data are for the pixel in column 0, which contains table[1] samples. Each channel contains table[width-1] samples in total.

Unpacked deep data chunks

When decompressed, the unpacked chunk consists of the channel data stored in a non-interleaved fashion:

```
pixel sample data for channel 0
pixel sample data for channel 1
pixel sample data for channel ...
pixel sample data for channel n
```

Exception: For ZIP_COMPRESSION only there will be up to 16 scanlines in the packed sample data block:

```
pixel sample data for channel 0 for scanline 0
pixel sample data for channel 1 for scanline 0
pixel sample data for channel ... for scanline 0
pixel sample data for channel n for scanline 0

pixel sample data for channel 0 for scanline 1
pixel sample data for channel 1 for scanline 1
pixel sample data for channel ... for scanline 1
pixel sample data for channel n for scanline 1

...
```

Deep data compression

The following compression schemes are the only ones permitted for deep data:

compression method	number of scan lines per block
NO_COMPRESSION	1
RLE_COMPRESSION	1
ZIPS_COMPRESSION	1
ZIP_COMPRESSION	16

Predefined Attribute Types

The IlmImf library predefines the following attribute types:

type name	data												
box2i	Four ints: xMin, yMin, xMax, yMax												
box2f	Four floats: xMin, yMin, xMax, yMax												
chlist	A sequence of channels followed by a null byte (0x00). Channel layout: <table><tr><td>name</td><td>zero-terminated string, from 1 to 255 bytes long</td></tr><tr><td>pixel type</td><td>int, possible values are: UINT = 0 HALF = 1 FLOAT = 2</td></tr><tr><td>pLinear</td><td>unsigned char, possible values are 0 and 1</td></tr><tr><td>reserved</td><td>three chars, should be zero</td></tr><tr><td>xSampling</td><td>int</td></tr><tr><td>ySampling</td><td>int</td></tr></table>	name	zero-terminated string, from 1 to 255 bytes long	pixel type	int, possible values are: UINT = 0 HALF = 1 FLOAT = 2	pLinear	unsigned char, possible values are 0 and 1	reserved	three chars, should be zero	xSampling	int	ySampling	int
name	zero-terminated string, from 1 to 255 bytes long												
pixel type	int, possible values are: UINT = 0 HALF = 1 FLOAT = 2												
pLinear	unsigned char, possible values are 0 and 1												
reserved	three chars, should be zero												
xSampling	int												
ySampling	int												
chromaticities	Eight floats: redX, redY, greenX, greenY, blueX, blueY, whiteX, whiteY												

type name	data
compression	unsigned char, possible values are NO_COMPRESSION = 0 RLE_COMPRESSION = 1 ZIPS_COMPRESSION = 2 ZIP_COMPRESSION = 3 PIZ_COMPRESSION = 4 PXR24_COMPRESSION = 5 B44_COMPRESSION = 6 B44A_COMPRESSION = 7
double	double
envmap	unsigned char, possible values are: ENVMAP_LATLONG = 0 ENVMAP_CUBE = 1
float	float
int	int
keycode	Seven ints: filmMfcCode, filmType, prefix, count, perfOffset, perfsPerFrame, perfsPerCount
lineOrder	unsigned char, possible values are: INCREASING_Y = 0 DECREASING_Y = 1 RANDOM_Y = 2
m33f	9 floats
m44f	16 floats
preview	Two unsigned ints, width and height, followed by 4×width×height unsigned chars of pixel data. Scan lines are stored top to bottom; within a scan line pixels are stored from left to right. A pixel consists of four unsigned chars, R, G, B, A.
rational	An int, followed by an unsigned int.
string	String length, of type int, followed by a sequence of chars.
stringvector	A sequence of zero or more text strings. Each string is represented as a string length, of type int, followed by a sequence of chars. The number of strings can be inferred from the total attribute size (see the Attribute \$a%out section, on page 8).

type name	data
tiledesc	Two unsigned ints: xSize, ySize, followed by mode, of type unsigned char, where mode = levelMode + roundingMode×16 Possible values for levelMode: ONE_LEVEL = 0 MIPMAP_LEVELS = 1 RIPMAP_LEVELS = 2 Possible values for roundingMode: ROUND_DOWN = 0 ROUND_UP = 1
timecode	Two unsigned ints: timeAndFlags, userData.
v2i	Two ints
v2f	Two floats
v3i	Three ints.
v3f	Three floats.

2ample File

The following is an annotated byte-by-byte listing of a complete OpenEXR file. The file contains a scan-line based image with four by three pixels. The image has two channels: G, of type HALF, and Z, of type FLOAT. The pixel data are not compressed. The entire file is 415 bytes long.

The first line of text in each of the gray boxes below lists up to 16 bytes of the file in hexadecimal notation. The second line in each box shows how the bytes are grouped into integers, floating-point numbers and text strings. The third and fourth lines indicate how those basic objects form compound objects such as attributes or the line offset table.

76	2f	31	01	02	00	00	00	63	68	61	6e	6e	65	6c	73
20000630				2				c h a n n e l s							
magic number				version, flags				attribute name							
								start of header							

00	63	68	6c	69	73	74	00	25	00	00	00	47	00	01	00
\0		c		h		l		i		s		t		\0	
								37				G		\0	
														HALF	


```

00 00 00 00 00 00 01 00 00 00 01 00 00 00 5a 00
      | 0 |      0      |      1      |      1      | z \0 |

```

```

02 00 00 00 00 00 00 00 01 00 00 00 01 00 00 00
FLOAT      | 0 |      0      |      1      |      1      |

```

```

00 63 6f 6d 70 72 65 73 73 69 6f 6e 00 63 6f 6d
\0 | c o m p r e s s i o n \0 | c o m
   | attribute name           | attribute type

```

```

70 72 65 73 73 69 6f 6e 00 01 00 00 00 00 64 61
p r e s s i o n \0 |      1      | NONE| d a
                  | attribute size |value|

```

```

74 61 57 69 6e 64 6f 77 00 62 6f 78 32 69 00 10
t a W i n d o w \0 | b o x 2 i \0 |
attribute name           | attribute type

```

```

00 00 00 00 00 00 00 00 00 00 00 03 00 00 00 02
   16      |      0      |      0      |      3      |
attribute size| attribute value

```

```

00 00 00 64 69 73 70 6c 61 79 57 69 6e 64 6f 77
   2      | d i s p l a y W i n d o w
          | attribute name

```

```

00 62 6f 78 32 69 00 10 00 00 00 00 00 00 00 00
\0 | b o x 2 i \0 |      16      |      0      |
   | attribute type           | attribute size | attribute value

```

```

00 00 00 03 00 00 00 02 00 00 00 6c 69 6e 65 4f

```

0		3		2		l i n e O
					attribute name	

72	64	65	72	00	6c	69	6e	65	4f	72	64	65	72	00	01	
r	d	e	r	\0		l	i	n	e	O	r	d	e	r	\0	
					attribute type											

00	00	00	00	70	69	78	65	6c	41	73	70	65	63	74	52			
1					INCY		p	i	x	e	l	A	s	p	e	c	t	R
attribute size					value					attribute name								

61	74	69	6f	00	66	6c	6f	61	74	00	04	00	00	00	00		
a	t	i	o	\0		f	l	o	a	t	\0		4				
					attribute type									attribute size			

00	80	3f	73	63	72	65	65	6e	57	69	6e	64	6f	77	43	
1.0					s c r e e n				W i n d o w				C			
attribute value					attribute name											

65	6e	74	65	72	00	76	32	66	00	08	00	00	00	00	00	
e	n	t	e	r	\0		v	2	f	\0		8				
					attribute type									attribute size		

00	00	00	00	00	00	73	63	72	65	65	6e	57	69	6e	64	
0.0					0.0					s c r e e n				W i n d		
attribute value									attribute name							

6f	77	57	69	64	74	68	00	66	6c	6f	61	74	00	04	00
o	w	W	i	d	t	h	\0		f	l	o	a	t	\0	
					attribute type										

00	00	00	00	80	3f	00	3f	01	00	00	00	00	00	00	5f	
4						1.0					\0					
								319								

size	attribute value		offset of scan line 0	
end of header			start of scan line offset table	

01	00	00	00	00	00	00	7f	01	00	00	00	00	00	00	00
351								383							
offset of scan line 1								offset of scan line 2							
end of scan line offset table															

00	00	00	18	00	00	00	00	00	54	29	d5	35	e8	2d	5c
0		24		0.000		0.042		0.365		0.092					
y		pixel data size		pixel data for G channel											
scan line 0															

28	81	3a	cf	e1	34	3e	8b	0b	bb	3d	89	74	f9	3e	01		
0.000985395					0.176643					0.0913306					0.487217		
pixel data for Z channel																	

00	00	00	18	00	00	00	37	38	76	33	74	3b	73	38	7f
1		24		0.527		0.233		0.932		0.556					
y		pixel data size		pixel data for G channel											
scan line 1															

ab	e8	3e	8a	cf	54	3f	5b	6c	11	3f	20	35	50	3d	02		
0.454433					0.831292					0.56806					0.0508319		
pixel data for Z channel																	

00	00	00	18	00	00	00	23	3a	0a	34	02	3b	5d	3b	38
2		24		0.767		0.252		0.876		0.920					
y		pixel data size		pixel data for G channel											
scan line 2															

f3	9a	3c	4d	ad	98	3e	1c	14	08	3f	4c	f3	03	3f		
0.0189148					0.298197					0.531557					0.515431	
pixel data for Z channel																
end of file																